Digital Communication in the Modern World Data Link Layer: Multi Access Protocols

http://www.cs.huji.ac.il/~com1 com1@cs.huji.ac.il

Some of the slides have been borrowed from: Computer Networking: A Top Down Approach Featuring the Internet, 3rd edition. Jim Kurose, Keith Ross Addison-Wesley, July 2004.

Intro to the Data Link Layer

Travel analogy

- University sends you to a conference in India
 - o taxi: Jerusalem to Ben-Gurion
 - o plane: Ben-Gurion to Mumbai
 - o plane: Mumbai to Chennai
 - o rickshaw: Chennai to conference center
- □ student = datagram
- university = sending node (application layer)
- travel agent = routing algorithm (network layer)
- □ transportation mode = data link layer protocol, i.e. running an airline is different than a rickshaw
- □ travel segment = communication link (physical layer)

DataLink Layer

"link"

Link Layer

- Introduction and services
- Error detection and correction
- Multiple access protocols
- Link-Layer Addressing
- □ Ethernet
- Hubs and switches
- PPP

DataLink Layer

Link Layer

Some terminology:

- hosts and routers are nodes
- communication channels that connect adjacent nodes along communication path are links
 - o wired links
 - wireless links
 - LANs
- layer-2 packet is a frame, encapsulates datagram

data-link layer has responsibility of transferring datagram from one node to adjacent node over a single link

DataLink Layer

Link layer

- In the Link layer there are different link types and they have different protocols
- Frame transferred by different link protocols over different links (decided by the network layer):
 - e.g., Ethernet on first link, frame relay on intermediate links, 802.11 on last link
- Each link protocol provides different services
 - o e.g., may or may not provide rdt over link; flow control; etc.
- Link types are grouped into:
 - o point-to-point (e.g. between routers, host to ISP, etc.)
 - o Broadcast (LAN, wireless)

Link Layer Services

■ Framing, link access:

- o encapsulate datagram into frame, adding header, trailer
- o channel access if shared medium
- "MAC" addresses used in frame headers to identify source, dest
 - different from IP address!

Reliable delivery between adjacent nodes

- o similar service as in the transport layer
- seldom used on low bit-error link (fiber, some twisted pair)
- o wireless links: high error rates
 - · Q: why both link-level and end-to-end reliability?


DataLink Layer

Link Layer Services (more)

- □ Flow Control:
 - o pacing between adjacent sending and receiving nodes
- Error Detection: (e.g. parity check, CRC)
 - o errors caused by signal attenuation, noise.
 - o receiver detects presence of errors:
 - · signals sender for retransmission or drops frame
- □ Error Correction: (e.g. two Dimensional Bit Parity)
 - o receiver identifies and corrects bit error(s) without resorting to retransmission
- Half-duplex and full-duplex
 - o with half duplex, nodes at both ends of link can transmit, but not at same time

DataLink Layer

Adaptors (aka NICs)



- □ link layer implemented in □ receiving side "adaptor"
 - Ethernet card, PCMCI card, 802.11 card
- sending side:
 - o encapsulates datagram in a frame
 - o adds error checking bits, rdt, flow control, etc.
- o looks for errors, rdt, flow control, etc
- o extracts datagram, passes to receiving node

DataLink Layer

Multiple Access Links and Protocols

Two types of "links":

- □ point-to-point <= Single access
 - o PPP for dial-up access (between host and ISP)
 - o point-to-point link between Ethernet switch and host
- broadcast (shared wire or medium) <= Multiple Access</p>
 - o traditional Ethernet
 - 802,11 wireless LAN











DataLink Laver

Multiple Access protocols

- single shared broadcast channel
- two or more simultaneous transmissions by nodes: interference
 - o collision if node receives two or more signals at the same time
- "Cocktail Party effect" ("popolitika behavior")

multiple access protocol

- distributed algorithm that determines how nodes share channel, i.e., determine when node can transmit
- communication about channel sharing must use channel itself!
 - no out-of-band channel for coordination

DataLink Laver

"Ideal" Multiple Access Protocol

Broadcast channel of bandwidth R bps

- 1. When one node wants to transmit, it can send at rate R bps.
- 2. When M nodes want to transmit, each can send at average rate R/M bps
- 3. Fully decentralized:
 - o no special node to coordinate transmissions
 - o no synchronization of clocks or slots
- 4. Simple

MAC Protocols: a taxonomy

Three broad classes:


- Channel Partitioning
 - o divide channel into smaller "pieces" (time slots. frequency, code)
 - o allocate piece to node for exclusive use
- Random Access
 - o channel not divided, allow collisions
 - o try to maximize probability that "everything will be ok"
- "Takina turns"
 - O Nodes take turns, but nodes with more to send can take longer turns

DataLink Layer

Channel Partitioning MAC protocols: TDMA

TDMA: time division multiple access

- □ access to channel in "rounds"
- each station gets fixed length slot in each round (length = packet transmission time)
- unused slots go idle
- example: 6-station LAN, 1,3,4 have pkt, slots 2,5,6 idle




DataLink Layer 1

Channel Partitioning MAC protocols: FDMA

FDMA: frequency division multiple access

- channel spectrum divided into frequency bands
- each station assigned fixed frequency band
- unused transmission time in frequency bands go idle
- example: 6-station LAN, 1,3,4 have pkt, frequency bands 2,5,6 idle



DataLink Layer

Code Division Multiple Access (CDMA)

- used in several wireless broadcast channels standards (cellular, satellite, etc)
- unique "code" assigned to each user; i.e., code set partitioning
- all users share same frequency, but each user has own "chipping" sequence (i.e., code) to encode data
- encoded signal = (original data) X (chipping sequence)
- decoding: inner-product of encoded signal and chipping sequence
- allows multiple users to "coexist" and transmit simultaneously with minimal interference (if codes are "orthogonal")

Data Link Layer 15


Code Division Multiple Access (CDMA)

- □ Code vector \overrightarrow{C} = $(c_1, c_2, ..., c_m, ..., c_M)$; $c_i \in \{1, -1\}$
- □ Let d_i denote data bit i and c_m code bit m,
- \square Let $Z_{i,m} := d_i \cdot c_m$
- □ Then:

$$d_{i} = \frac{1}{M} \sum_{m=1}^{M} (d_{i} \cdot c_{m}) \cdot c_{m} = \frac{1}{M} \sum_{m=1}^{M} Z_{i,m} \cdot c_{m}$$


Data Link Layer

CDMA Encode/Decode



Data Link Layer 17

CDMA: two-sender interference



Random Access Protocols

- □ When node has some packet to send
 - o transmit at full channel data rate R.
 - o no a priori coordination among nodes
- two or more transmitting nodes → "collision",
- random access MAC protocol specifies:
 - o how to detect collisions
 - o how to recover from collisions (e.g., via delayed retransmissions)
- Examples of random access MAC protocols:
 - o slotted ALOHA
 - ALOHA
 - O CSMA, CSMA/CD, CSMA/CA

DataLink Layer 19

Slotted ALOHA

Assumptions


- □ all frames same size
- time is divided into equal size slots = time to transmit 1 frame
- nodes start to transmit frames only at beginning of slots
- nodes are synchronized
- if 2 or more nodes transmit in slot, all nodes detect collision

Operation

- when node obtains fresh frame, it transmits in next slot
- no collision, node can send new frame in next slot
- if collision, node retransmits frame in each subsequent slot with prob. p until success

DataLink Layer

Slotted ALOHA



Pros

- single active node can continuously transmit at full rate of channel
- decentralized:
 although slots in nodes
 need to be in sync
- □ simple

Cons

- collisions, wasting slots
- idle slots
- nodes may be able to detect collision in less than time to transmit packet
- clock synchronization

DataLink Layer

Slotted Aloha efficiency

Efficiency is the long-run fraction of successful slots when there are many nodes, each with many frames to send

- Suppose N nodes with many frames to send, each transmits in slot with probability p
- □ prob that node "#1" has success in a slot = p(1-p)^{N-1}
- prob that any node has a success = Np(1-p)^{N-1}


- □ For max efficiency with N nodes, find p* that maximizes Np(1-p)^{N-1}
- □ For many nodes, take limit of Np*(1-p*) $^{N-1}$ as N goes to infinity, gives p*= 1/e \approx 0.37

At best: channel used for useful transmissions 37% of time!

DataLink Layer

Pure (unslotted) ALOHA

- unslotted Aloha: simpler, no synchronization
- $lue{}$ when frame first arrives
 - o transmit immediately
- collision probability increases:
 - frame sent at t_0 collides with other frames sent in $[t_0-1,t_0+1]$



Pure Aloha efficiency

P(success by given node) = P(node transmits) .

P(no other node transmits in $[t_0-1,t_0]$ · P(no other node transmits in $[t_0,t_0+1]$ = $p \cdot (1-p)^{N-1} \cdot (1-p)^{N-1}$ = $p \cdot (1-p)^{2(N-1)}$

... choosing optimum p and then letting $n \rightarrow infinity ...$

Even worse!

 $p* = 1/(2e) \approx 0.18$

CSMA (Carrier Sense Multiple Access)

CSMA: listen before transmit:

If channel sensed idle: transmit entire frame

- □ If channel sensed busy, defer transmission
- Human analogy: don't interrupt others that already talk

DataLink Layer 25

CSMA collisions

collisions can still occur:


propagation delay means two nodes may not hear each other's transmission

collision:

entire packet transmission time wasted

note:

role of distance & propagation delay in determining collision probability




CSMA/CD (Collision Detection)

CSMA/CD: carrier sensing, deferral as in CSMA

- o collisions detected within short time
- colliding transmissions aborted, reducing channel wastage
- collision detection:
 - easy in wired LANs: measure signal strengths, compare transmitted, received signals
 - difficult in wireless LANs: receiver shut off while transmitting
- human analogy: the polite conversationalist

DataLink Layer 27

CSMA/CD collision detection



DataLink Layer

"Taking Turns" MAC protocols

channel partitioning MAC protocols:

- o share channel efficiently and fairly at high load
- inefficient at low load: delay in channel access,
 1/N bandwidth allocated even if only 1 active node!

Random access MAC protocols

- efficient at low load: single node can fully utilize channel
- high load: collision overhead

"taking turns" protocols

look for best of both worlds!


"Taking Turns" MAC protocols

Polling:

- master node "invites" slave nodes to transmit in turn
- concerns:
 - o polling overhead
 - latency
 - single point of failure (master)

Token passing:

- control token passed from one node to next sequentially.
- □ token message
- concerns:
 - o token overhead
 - latency
 - single point of failure (token)



Summary of MAC protocols

□ What do you do with a shared media?

- Channel Partitioning (a priori division):
 - · Time Division, Frequency Division, Code division
- Random partitioning (dynamic):
 - · ALOHA, S-ALOHA, CSMA, CSMA/CD
 - Carrier sensing: easy in some technologies (wire), hard in others (wireless)
 - · CSMA/CD used in Ethernet
 - · CSMA/CA used in 802.11
- Taking Turns
 - · polling from a central site
 - · token passing